

LVM on loop persistent

LVM ?? lopp ?????????????? ?????? ?????????????????

???? ?????????? :???? ?????????? LVM ?????? /dev/loopX ?????????? ?? ?????? ?????????????? ?????????? ?????? losetup ??????????
????????????????? ?? ?????????? ?????????? ?????????? ?????? ?????????????????? Volume

/etc/systemd/system/loops-setup.service

```
[Unit]
Description=Setup loopback devices

DefaultDependencies=no
Conflicts=umount.target

Requires=lvm2-lvmetad.service -.mount
Before=local-fs.target umount.target
After=lvm2-lvmetad.service mnt-host.mount

[Service]
ExecStart=/bin/bash -x -c "/sbin/losetup /dev/loop0 /disk1.img; /sbin/losetup /dev/loop1 /disk2.img"
ExecStop=/bin/bash -x -c "/sbin/losetup -d /dev/loop0; /sbin/losetup -d /dev/loop1"

RemainAfterExit=yes
Type=oneshot

[Install]
WantedBy=local-fs-pre.target
```

systemctl enable loops-setup.service

?????? ?? ?????????? ?????????? - ??? **-.mount** ? ?????????? ??? ??? ?????? ?????????????? ? ?????????? ?????????? ?? ??????? 18

-.mount

????????? ??? ???:

```
systemctl | grep mount
...
-.mount          loaded active mounted /
...
```